How the whole data collecting works:

- 1. Use Azure.py to collect rgb, depthmap and intrinsic matrix.
- 2. With the data we get from step 1, use Quan Miao's program to get every frame's corresponding rgb, depthmap, mask, bounding box, intrinsic and extrinsic matrix.
- 3. Generate corresponding 2d 3d points through 3d 2d.py with the data from step 2.

I will set all the file directory for you, and will tell you where to put what data.

Azure.py part:

The rgb image will be put under ./rgb.

The depth map will be put under ./depth_map

The intrinsic matrix for depth camera will be put under ./intrinsic_depth

The intrinsic matrix for color camera will be put under ./intrinsic_rgb

Azure.py also has some commented lines to get imu_data/point_cloud/mask/bounding_box.

```
config = k4a.Config(
    color_resolution=k4a.ColorResolution.RES_720P,
    depth_mode=k4a.DepthMode.WFOV_2X2BINNED,
    synchronized_images_only=True,
    camera_fps=k4a.FPS.FPS_30,
)
```

Here to change the settings of cameras. First line to changes resolution color camera, second line changes depth camera, last line changes fps.

3d_2d.py part:

Here, all the data is from Quan Miao's program.

The intrinsics.json should be put under ./dataset
The depth.png should be put under ./dataset/depth
The mask.png should be put under ./dataset/mask
The pose.npy should be put under ./dataset/pose
The rgb.png should be put under ./dataset/rgb

The results from 3d_2d.py will be put under:

The point_cloud.ply will be put under ./dataset/point_cloud
The 2d_array.pkl and 2d_array.txt will be put under ./dataset/2d_array
The 3d_array.pkl and 3d_array.txt will be put under ./dataset/3d_array

Note: All the data should be named from 0, for example: 0.png, 1.png, 2.png...

You must have the same number of files of depthmap, mask, pose and rgb.

How to test if the result is right:

Use the first module of test.ipynb:

Change the path in:

```
points_2d = np.loadtxt("./dataset/2d_array/0.txt")
points_3d = np.loadtxt("./dataset/3d_array/0.txt")
```

Under our test, the error is 1/(640x480), this error may float a litte, but won't much. It is caused by the float to int during 3d to 2d.

You can change the error threshold here, now it's set to 1:

```
if error > 1:
    print('2D and 3D points do not correspond.')
    else:
       print('2D and 3D points correspond.')
```

The pickle format test is commented under loadtxt, just comment txt loading and make pickle reading valid, you can test pickle files.